

Aurora Ingest Version 6.5.2 Release Notes and Upgrade Instructions

These release notes contain the most recent information and supersede previous publications, as of 31 August 2009. Check the Grass Valley website at *www.grassvalley.com/docs* for an updated version that contains additional important information.

Copyright © Grass Valley, Inc. All rights reserved. Printed in the United States of America. Portions of software © 2000 – 2009, Microsoft Corporation. All rights reserved. This document may not be copied in whole or in part, or otherwise reproduced except as specifically permitted under U.S. copyright law, without the prior written consent of Grass Valley, Inc., P.O. Box 59900, Nevada City, California 95959-7900. This product may be covered by one or more U.S. and foreign patents.

Product options and specifications subject to change without notice. The information in this manual is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Grass Valley, Inc. Grass Valley, Inc. assumes no responsibility or liability for any errors or inaccuracies that may appear in this publication.

Grass Valley, K2, Aurora, Summit, Dyno, Turbo, M-Series, Profile, Profile XP, NetCentral, NewsBrowse, NewsEdit, NewsQ, NewsShare, NewsQ Pro, and Media Manager are either registered trademarks or trademarks of Grass Valley, Inc. in the United States and/or other countries. Grass Valley, Inc. products are covered by U.S. and foreign patents, issued and pending. Additional information regarding Grass Valley, Inc.'s trademarks and other proprietary rights may be found at www.thomsongrassvalley.com. Other trademarks and logos used in this document are either registered trademarks of the manufacturers or vendors of the associated products, such as Microsoft® Windows® operating system, Windows Media® player, Internet Explore® internet browser, and SQL Server™. QuickTime and the QuickTime logo are trademarks or registered trademarks of Apple Computer, Inc., used under license therefrom.

Contents

Grass Valley Product Support	3
Release Summary What's new in version 6.5.2. Fixed in 6.5.2. Feature limitation in this release. Changes and features in previous releases. Version 6.5.1.132. Version 6.5. Older versions.	5 5 6 6 6 6 6
Version compatibility System specifications Compatible Grass Valley products Compatible third party products	9 9 11 12
Upgrading Aurora Ingest systems. Upgrading Aurora Ingest devices with SiteConfig. About upgrading Aurora Ingest devices with SiteConfig. Prepare for upgrade. Prepare SiteConfig for software deployment. Upgrade K2 systems. Distribute devices into deployment groups. Install High Priority Windows updates (recommended). Manually upgrade systems. Check all currently installed software on Aurora Ingest devices. Add software package to deployment group for Aurora Ingest devices. Setting deployment options. Upgrade NAS systems. Upgrade Browse and MediaFrame systems.	13 13 13 14 14 15 16 16 16 17 18 21 23 24
Licensing Grass Valley products About software licensing Requesting a license Adding a license Deleting licenses Archiving licenses Aurora Ingest licenses	25 25 27 27 27 27 28 28
Operation considerations	29
Additional notes Installing software Configuring ScheduALL properties Configuring ScheduALL application	32 33 35 39
	41

Grass Valley Product Support

To get technical assistance, check on the status of a question, or to report a new issues, contact Grass Valley Product Support via e-mail, the Web, or by phone or fax.

Web Technical Support

To access support information on the Web, visit the product support Web page on the Grass Valley Web site. You can download software or find solutions to problems.

World Wide Web: http://www.grassvalley.com/support/

Technical Support E-mail Address: gvgtechsupport@grassvalley.com

Telephone Support

Use the following information to contact Product Support by phone.

International Support Centers

Our international support centers are available 24 hours a day, 7 days a week.

Support Center	Toll free	In country
France	+800 80 80 20 20	+33 1 48 25 20 20
United States	+1 800 547 8949	+1 530 478 4148

Authorized Local Support Representative

A local support representative may be available in your country. To locate a support center during normal local business hours, refer to the following list. This list is regularly updated on the website for Grass Valley Product Support

(http://www.grassvalley.com/support/contact/phone/)

After-hours local phone support is also available for warranty and contract customers.

Region	County	Telephone
Asia	China	+86 10 5883 7575
	Hong Kong, Taiwan, Korea, Macau	+852 2531 3058
	Japan	+81 3 6848 5561
	Southeast Asia - Malaysia	+603 7492 3303
	Southeast Asia - Singapore	+65 6379 1769

Grass Valley Product Support

Region	County	Telephone
	Indian Subcontinent	+91 11 515 282 502; +91 11 515 282 504
Pacific	Australia, New Zealand	+61 1300 721 495
Central America, South America	All	+55 11 5509 3440
North America	North America, Mexico, Caribbean	+1 800 547 8949; +1 530 478 4148
Europe	UK, Ireland, Israel	+44 118 923 0499
	Benelux – Netherlands	+31 (0) 35 62 38 421
	Benelux – Belgium	+32 (0) 2 334 90 30
	France	+800 80 80 20 20; +33 1 48 25 20 20
	Germany, Austria, Eastern Europe	+49 6150 104 444
	Belarus, Russia, Tadzhikistan, Ukraine, Uzbekistan	+7 095 258 09 20; +33 (0) 2 334 90 30
	Nordics (Norway, Sweden, Finland, Denmark, Iceland)	+45 40 47 22 37
	Southern Europe – Italy	+39 02 24 13 16 01; +39 06 87 20 35 42
	Southern Europe – Spain	+34 91 512 03 50
Middle East, Near East,	Middle East	+971 4 299 64 40
Africa	Near East and Africa	+800 80 80 20 20; +33 1 48 25 20 20

Release Summary

What's new in version 6.5.2

This version of software includes several improvements, in addition to correcting some problems that were present in earlier releases.

Version 6.5.2

- Scheduling integration with VizuAll, Inc.'s ScheduALL Enabling events scheduled on Aurora Ingest Scheduler to appear on ScheduALL and vice versa.
- SiteConfig support Network configuration and software deployment across all Aurora products is supported by SiteConfig, Grass Valley's system management tool.
- Administrator password The default administrator account on Aurora devices has credentials as follows:
 - Username: administrator
 - Password: adminGV!

SiteConfig expects these credentials by default.

- **Records survive on Ingest Server close** Users are now able to close the Aurora Ingest Server while recording is taking place. Records will continue for the predetermined duration, regardless of whether the server application is launched again.
- **Documentation for this release** The following manuals have been revised or are new:
 - Aurora Ingest System Guide 071-8514-05
 - SiteConfig Migration Instructions 071-8705-00

The manuals are on Aurora Ingest Software CD part number 063-8268-09.

Fixed in 6.5.2

Reference number	Description
CR101934	RMI import of trimmed XDCAM HD clip results in corrupted clip in News database.
CR102312	Scheduler can skip past an event and leave it in "Ready" status.
CR102334	On system with full SQL installed, Ingest installer gives error that SQL Express is not installed.
CR103947	Event stays as recording when SD K2 had stopped recording.
CR104457	Reordering templates no longer works.

Release Summary

Reference number	Description
CR104465	VTR Controller/VTR Ingest won't launch on Marathon systems.
CR104900	After using Scheduler to record to placeholder on main and backup server, clip starts on different frame when loaded in main vs. backup Playout.

Feature limitation in this release

• No nested bin support with K2 Summit.

Changes and features in previous releases

The following sections describe changes and features in past releases.

Version 6.5.1.132

• **K2 Summit compatible** – The Aurora suite of software, including Aurora Ingest, is compatible with the K2 Summit software.

Version 6.5

Aurora Ingest 6.5 is a major release for Aurora Ingest. Although each application has new features and functionality, the overarching change is the inclusion of MediaFrame. A complete, in-depth guide to what's new is included in a document called What's New – Aurora Ingest 6.5.

Aurora Ingest Server

• MediaFrame Integration – New search and metadata tools have been embedded in numerous areas within the application. MediaFrame server can be configured within Tools | Options of Aurora Ingest - Server.

NOTE: For MediaFrame connectivity to function between the Scheduler, RMI, and the VTR Ingest applications that are on a different domain than the MediaFrame server, there must be a defined one-way trust relationship between Aurora Ingest and the MediaFrame Server.

- Time of Day Timecode Users can now select Time of Day timecode for feeds.
- MediaFrame Expiration Date Setting Users can set expiration date for metadata that ties into MediaFrame.

Aurora Ingest Scheduler

• MediaFrame Integration – Users can search, preview and mark highlights directly from the scheduling application.

- Improved Crash Record Control Users can name crash records, select router source, select aspect ratio setting and direct a crash record to a folder location, prior to hitting record. These actions lead to a faster scheduling operation.
- **Quick Schedule** Users can use Quick Schedule mode to the Scheduler grid for efficient additions of feeds.
- Enhanced Trim and Extend Users can trim and extend feeds via keyboard.
- **X-Keys controller Support** X-Keys controller is supported with Scheduler and MediaFrame to enhance the ability to log live and previously captured events.
- System Information Utility The Help->About box now includes a System Information Utility.
- Link to Placeholder A currently recording event can be linked to a placeholder.
- **Default Colors** A new set of default colors have been configured for Scheduler. If needed, users can still change those default colors within **Tools | Options**.

Aurora Ingest RMI

- **MediaFrame Integration** When MediaFrame is enabled, metadata can be mapped from the removable media device to MediaFrame.
- Multiple Clips Merge Users can merge multiple clips into a single clip on import.
- Preview and Trim Users can preview and trim clips prior to import.
- **Speed Improvement** Speed improvement after the need to transcode on import had been eliminated.
- Edit During Import Currently importing feeds are editable by Aurora Edit before they are complete.
- **DV100 Support** Support for DV100 media, via removable media import from P2.

NOTE: Transfers of DV100 media to the Summit are supported, while transfers to K2 server are not.

- AVC-Intra Support Support for AVC-Intra media import.
- **XDCAM HD 1080i Support** Support for XDCAM 4:2:2, 1080i, Long GOP 50mbit media import.

NOTE: XDCAM HD 720p import format is not yet supported.

- **System Information Utility** The Help->About box now includes a System Information Utility.
- **Default Colors** Default colors have been changed for RMI.

Aurora Ingest VTR Ingest

- MediaFrame Integration When MediaFrame is enabled, metadata can be added either on a tape basis or clip by clip basis.
- **Keyword Scan** Keyword scan feature automatically records an entire tape and marks keywords for every timecode break that is found.
- **Primary and backup records** Users can now make primary and backup records.
- **System Information Utility** The Help->About box now includes a System Information Utility.

Older versions

For information about older software versions not listed in these release notes, refer to the release notes for those versions.

Version compatibility

Versions qualified for compatibility with this release of software are summarized in the following sections.

System specifications

This section describes the hardware requirements that customers should use when purchasing equipment for this release. The minimum spec describes the bare minimum requirement for running Aurora, which may reduce the quality of user experience, depending on the task. The expected lifespan of minimum spec equipment is also less than that of recommended spec equipment, since it lacks head room for future growth.

NOTE: Minimum specs for SD configurations are provided only for existing SD customers upgrading to this release. New customers should use HD configurations.

	MINIMUM Spec	RECOMMENDED Spec	
Processor(s)	Intel Core 2 Quad Core 2.33 GHz	Two Intel Xeon 5410 Quad Core 2.33 GHz	
	OR		
	Two Intel Xeon 5160 Dual Core 3.0 GHz		
Memory	3 GB	3 GB	
Graphics	Discrete graphics with 256 MB of dedicated memory and support for Direct3D 9 and Shader Model 3.0	Discrete graphics with 384 MB of dedicated memory and support for Direct3D 9 + 10 and Shader Model 4.0	
System Drive	80 GB 7200 RPM SATA	80 GB 7200 RPM SATA	
Media Drives	2 x 250 GB 7200 RPM SATA striped	2 x 250 GB 7200 RPM SATA striped	
Optical Drive	CD/DVD	CD/DVD	
Network	Gigabit Ethernet (2)	Gigabit Ethernet (2)	
Firewire/1394	As needed	As needed	
OS	Windows XP Pro 32 SP3	Windows XP Pro 32 SP3	
Notes	A Gigabit Ethernet card and a be installed on the same PCI slots), since this can cause ve customer's responsibility to e sufficient number and type of	A Gigabit Ethernet card and a Firewire/1394 card shall NOT be installed on the same PCI bus segment (eg. adjacent PCI slots), since this can cause very poor performance. It is the customer's responsibility to ensure that the system has sufficient number and type of expansion slots to meet the	

Aurora Edit HD desktop, Aurora Ingest RMI (HD)

Version compatibility

	MINIMUM Spec	RECOMMENDED Spec
	intended use. (For example, to FireWire cards.)	accommodate network and/or
Aurora Ingest RMI (SD)		
	MINIMUM Spec	
Processor(s)	Intel Core 2 Dual Core 2.33 GHz	
	OR	
	Intel Xeon 5140 Dual Core 2.33 GHz	
	OR	
	AMD Opteron 270 Dual Core 2.0 GHz	
Memory	2 GB	
Graphics	Discrete graphics with 128 MB of dedicated memory and support for Direct3D 9 and Shader Model 3.0	
System Drive	80 GB 7200 RPM SATA	
Media Drives	2 x 250 GB 7200 RPM SATA striped	
Optical Drive	CD/DVD	
Network	Gigabit Ethernet (2)	
Firewire/1394	As needed	
OS	Windows XP Pro 32 SP3	
Notes	A Gigabit Ethernet card and a be installed on the same PCI slots), since this can cause ve	Firewire/1394 card shall NOT bus segment (eg. adjacent PCI ry poor performance.

Aurora Ingest Server

	MINIMUM Spec	RECOMMENDED Spec
Model	HP xw4600	Dell PowerEdge 2950
Processor	Intel Core 2 Dual Core 2.3 GHz	Intel Xeon 1.0 GHz
Memory	1 GB	2 GB

	MINIMUM Spec	RECOMMENDED Spec
Graphics	Integrated or discrete graphics with 128 MB of memory and support for Direct3D 9 and Shader Model 3.0	Integrated graphics
System Drive	80 GB 7200 RPM SATA	36 GB 7200 RPM SATA or SAS
Optical Drive	CD/DVD	CD/DVD
Network	Gigabit Ethernet	Gigabit Ethernet
OS	Windows XP Pro 32 SP3	Windows Server 2003 R2 32 SP2

Aurora Ingest (VTR Ingest, VTR Controller, Scheduler)

	MINIMUM Spec	RECOMMENDED Spec
Processor	Intel Core 2 Dual Core 2.3 GHz	Intel Core 2 Quad Core 2.3 GHz
Memory	1 GB	2 GB
Graphics	Integrated or discrete graphics with 128 MB of memory and support for Direct3D 9 and Shader Model 3.0	Integrated or discrete graphics with 128 MB of memory and support for Direct3D 9 and Shader Model 3.0
System Drive	80 GB 7200 RPM SATA	80 GB 7200 RPM SATA
Optical Drive	CD/DVD	CD/DVD
Network	Gigabit Ethernet	Gigabit Ethernet
OS	Windows XP Pro 32 SP3	Windows XP Pro 32 SP3
Notes	It is the customer's responsibility to ensure that the system has sufficient number and type of expansion slots to meet the intended use. AURORA_IN_BASE and AURORA_IN_LOGGER requires one free PCI slot for video capture board and one free PCI slot for Comtrol 422 board.	

Compatible Grass Valley products

Grass Valley products are compatible with this release of software as follows:

Product	Version	Comments
Aurora Browse client	6.5.2.8	—

Product	Version	Comments
Aurora Browse MediaFrame Server	6.5.2.19	With compatible version of SQL
Aurora Browse Proxy Encoder	6.5.2.12	_
Aurora Edit	6.5.2.745	With compatible version of SQL
Aurora Playout	6.5.2.80	With compatible version of SQL
Generic iSCSI Installer	3.3.0.1141 or 7.0.11.1081 or 7.0.12.1151	_
GVG_MLib Installer	3.3.0.1141 or 7.0.11.1081 or 7.0.12.1151	_
K2 system software	3.3.0.1141 or 7.0.11.1081 or 7.0.12.1151	With compatible version of SNFS
M-Series system software	2.0.13.567	_
RMI Core	6.5.2.745	For RMI Installation
SiteConfig application	1.1.0.433 or higher	—

Compatible third party products

Products by manufacturers other than Grass Valley are compatible with this release of software as follows:

Product	Version	Comments
DeckLink	6.4	
ENPS	5.00.0123 or 6.00.0009	For use with Scheduled Events
Hauppauge	5.9F	
Microsoft Windows	XP with Service Pack 3	Windows Vista is NOT currently supported
Microsoft Windows Server	Win2003 Server R2	For Ingest Server Component only
Panasonic P2 Driver	2.03.0002	Contact Panasonic for driver
SNFS	3.1.2.RC25225.6138	For RMI Installation within K2 SAN
Sony XDCAM FAM Driver	2.04	Contact Sony for driver

This section contains the tasks necessary for the upgrade to this release of software.

Upgrading Aurora Ingest devices with SiteConfig

This section contains the tasks for using SiteConfig to upgrade to this release of software. Work through the tasks sequentially to complete the upgrade.

NOTE: These upgrade instructions assume that current software is at version 6.5.0 or higher. If you have a lower version of software, contact Grass Valley Support before upgrading.

About upgrading Aurora Ingest devices with SiteConfig

These upgrade instructions apply to Aurora Ingest devices as follows:

- Aurora Ingest workstation
- IEP

With these upgrade instructions, you use SiteConfig from a network connected control point PC and remotely upgrade software simultaneously on one or more devices. This is the recommended process for software upgrades.

Before you upgrade software using SiteConfig, each Aurora Ingest device must be migrated to become a SiteConfig managed device. This includes installing SiteConfig support on the device and qualifying the device for communication with SiteConfig. Refer to *SiteConfig Migration Instructions*. Also refer to the *SiteConfig User Manual* or *SiteConfig Help Topics*.

NOTE: Do not attempt to upgrade software incrementally across the devices of a K2 SAN while media access is underway. Online software upgrading is not supported.

To upgrade software using SiteConfig, you must first have SiteConfig set up for system management and software deployment in your facility. These upgrade instructions assume that you have already done that for your K2 SAN. Then you add your Aurora Ingest devices to the SiteConfig system description that you are using for your K2 SAN.

The following installation tasks provide information specifically for the upgrade to this version of software. Read the information in these sections carefully before attempting any upgrade to software.

Prepare for upgrade

Before upgrading, do the following:

• Procure the software installation files for this release via the appropriate distibution method, such as download, CD-ROM, network drive, or external drive.

- Start up the devices you are upgrading, if they are not already started.
- Stop all media access on the devices you are upgrading.
- Shut down all applications on the devices you are upgrading.

Prepare SiteConfig for software deployment

Do the following to prepare SiteConfig for the software upgrade.

- 1. Make the following files accessible to the SiteConfig control point PC:
 - File for all Aurora Ingest devices:
 - Aurora Ingest software installation (*.cab) file
 - Additional files for Aurora Ingest RMI devices:
 - AuroraSuite software installation (*.cab) file
 - GenericISCI software installation (*.cab) file
 - GVGMLib software installation (*.cab) file
- 2. If a newer version of SiteConfig is available for upgrade and you have not yet upgraded SiteConfig, do the following:
 - a) From Windows Add/Remove programs, uninstall the current version of SiteConfig from the control point PC.
 - b) Install the new version of SiteConfig on the control point PC.
- 3. If not already present in the SiteConfig system description, configure deployment groups as follows:
 - A deployment group that contains your Aurora Ingest devices

Upgrade K2 systems

Prerequisites for this task are as follows:

• If upgrading a K2 SAN, all SAN clients must be offline (all media access stopped) or shut down. Depending on your system design, this could include devices such as K2 clients, K2 appliances, Aurora Proxy (Advanced) Encoders, MDI server, Aurora Edit clients, Aurora Ingest clients, Aurora Playout clients, and generic clients.

Upgrade your K2 systems to the compatible version of K2 system software. This includes K2 SAN systems and stand-alone K2 Media Client and K2 Summit Production Client systems. Refer to *K2 Release Notes* for procedures.

Distribute devices into deployment groups

You can gather devices of different types into a SiteConfig deployment group. This allows you to deploy software to all the devices in the deployment group at the same time, as part of the same deployment session. Based on the roles you have assigned to the devices, SiteConfig deploys the proper software to each device. This increases the efficiency of your software deployment with SiteConfig.

If you have not already done so, configure your deployment groups. The recommended deployment group distribution is as follows. Depending on your system design, your system might not have all the device types listed.

- In a deployment group named "Aurora_Edit_Ingest_Playout", place the following devices:
 - Aurora Edit workstation of any storage options: Shared storage, NAS storage, and stand-alone.
 - Aurora Edit LD
 - DSM
 - Conform Server
 - SmartBin Server
 - FTP Server
 - Aurora Ingest Platform
 - IEP
 - Aurora Playout Platform
- In a deployment group named "Aurora_Browse_MediaFrame", place the following devices:
 - MediaFrame server
 - MDI server
 - Aurora Proxy Encoder
 - K2 Basecamp Express
- If you have a K2 Nearline SAN (NAS), in a deployment group named for the SAN system, place the following devices:
 - The Nearline SAN's K2 Media Servers.

Install High Priority Windows updates (recommended)

• Windows "High Priority" updates are recommended, but not required. While you have devices in an offline state to upgrade software, you should check to see if there are any new updates that you need to install. Use standard Windows procedures.

△ CAUTION: Only "High Priority Updates" should be installed. Do not install other Windows or driver updates.

Manually upgrade systems

Some tasks that might be required with the upgrade to this release are not supported for SiteConfig management and/or software deployment. For these tasks you must manually upgrade and/or configure the device before using SiteConfig to upgrade software. Refer to the tasks in this section as appropriate for your system.

Upgrade Microsoft SQL Server 2005 Standard Edition

Microsoft SQL Server 2005 Standard Edition is installed on devices as follows:

- Aurora DSM SQL Server 2005 Standard Edition is required.
- Ingest Server Either Microsoft SQL Express 2005 or Microsoft SQL Server 2005 Standard Edition is required.

Use the following steps to manage upgrades to Microsoft SQL Server 2005 Standard Edition.

- 1. Determine if you have Microsoft SQL Server 2005 Standard Edition installed on one or more of your system devices, If installed, continue with next steps.
- 2. Check version compatibility information in these release notes and determine if this release of software requires an upgrade to Microsoft SQL Server 2005 Standard Edition.
- 3. If an upgrade is required, go to the local device and upgrade Microsoft SQL Server 2005 Standard Edition.

Check all currently installed software on Aurora Ingest devices

Prerequisites for this task are as follow:

- The device is assigned in the SiteConfig system description and network connectivity is present.
- SiteConfig is able to log in to the device using the username/password credentials assigned to the device.
- The SiteConfig control point PC does not have a network drive mapped to an administrative share (such as C\$) on a device on which you are checking software.
- If this is the first time deploying software to Aurora devices using SiteConfig, on those Aurora devices previous versions of Aurora software and SiteConfig software, such as the Network Configuration Kit and/or Discovery Agent, have been manually uninstalled. For more information refer to *SiteConfig Migration Instructions*.

Do the following steps on the devices that you are upgrading.

1. In the **Software Deployment | Deployment Groups** tree view, right-click the top-most node for the group or any individual device and select **Check Software**.

NOTE: If you have access problems, verify that the administrator account on the device has credentials as currently configured in SiteConfig. By default credentials on the device should be administrator/adminGV! for Aurora devices and Administrator/adminK2 for K2 devices. The Check Software dialog box appears. SiteConfig searches for software on the selected device or devices and gathers information. Progress is reported.

2. When the check is complete for the selected device or devices, close the Check Software dialog box.

An updated list of all currently installed software is displayed in the **Software Deployment | Devices | Installed Software** list view. If software is a SiteConfig managed software package, information is displayed in the Managed Package and Deployment Group columns.

Add software package to deployment group for Aurora Ingest devices

Prerequisites for this task are as follows:

- You can access the software package file from the SiteConfig control point PC.
- The Aurora Ingest devices to which you are deploying software are in a deployment group.

Use the following procedure to add one or more software packages to the deployment group that contains your Aurora Ingest devices. For this release of software, identify and add software installation files as follows:

Software	File name
Aurora Ingest software – For all Aurora Ingest devices	AuroraIngest_6.5.2.xxxx.cab
Aurora Suite – For Aurora Ingest RMI device only	AuroraSuite_6.5.2.xxxx.cab

For Aurora Ingest RMI devices, you must also add the following software packages to the deployment group. Depending on the K2 software version of your K2 SAN, also add software package installation files as follows:

NOTE: Add files for either 3.x OR 7.x. Do not add files for both 3.x AND 7.x.

• If your devices access storage on a K2 software version 3.x K2 SAN, add software package installation files as follows:

Software compatible with 3.x K2 SAN	File name
Generic iSCSI client	GenericISCI_x86_3.x.x.cab
GVG MLib software	GVG_MLib_3.x.x.cab

• If your devices access storage on a K2 software version 7.x K2 SAN, add software package installation files as follows:

Software compatible with 7.x K2 SAN	File name
Generic iSCSI client	GenericISCI_x86_7.x.x.cab
GVG MLib software	GVG_MLib_7.x.x.cab

SNFS is bundled with the Generic iSCSI cab file.

- 1. In the **Software Deployment | Deployment Groups** tree view, select a deployment group.
- 2. Click the Add button.

The Add Package(s) dialog box opens.

- 3. Do one of the following to select the software package:
 - Select from the list of packages then click **OK**.
 - Click Browse, browse to and select the package, then click Open.
- 4. If one or more EULAs are displayed, accept them to proceed. If you do not accept a EULA, the associated software is not assigned to the deployment group.

SiteConfig adds the package to the deployment group.

The package appears in the Managed Packages list for the selected deployment group. SiteConfig creates new software deployment tasks for the package and displays them in the Tasks list view.

Setting deployment options

Pre-requisites for this procedure are as follows:

- A software package has been assigned to the deployment group and applicable deployment tasks are now displayed in the Tasks area.
- 1. In the **Software Deployment | Deployment Groups** tree view, select a deployment group.
- 2. In the Tasks list view, view tasks and determine if you must set deployment options. Tasks that need to have deployment options set display in the Details column a message stating "Deployment options required."

If you select a task that needs to have its deployment options set, the Start Deployment button is disabled and the message is displayed next to the button.

- 3. Do one of the following to set deployment options:
 - Double-click the task.
 - Select the task and click the **Options** button.

A wizard opens.

4. Work through wizards and set deployment options as follows:

Software	Deployment options	
Aurora		
Ingest		

Depioyi	nent opt	ions					
Ingest							
Managed F	Packages						
Manageo	I Package				100000000000		CAR MODULAT
Discov	/eryAgent 1.0.12						
Tasks							
Deploy	Device	Managed Package	Action	Status	Details		
	Ingest	Auroralngest 6.5.2.139	Install		Deployment	t options required.	
	Ingest	IngestServerPrereq	Install				
Speci	erty Set Editor fy Aurora Inges	st Server Configuration	n				
Prope Speci	erty Set Editor ify Aurora Inge: y the SQL Server	at Server Configuration	n y Aurora Ing	jest Server.	t tit tit some det be de		
Specif	erty Set Editor ify Aurora Inge: y the SQL Server) Use SQL Expres	at Server Configuration configuration to be used b se 2005	n y Aurora Ing	jest Server.	1994 - San		
Speci Speci Speci O	erty Set Editor ify Aurora Inge: y the SQL Server) Use SQL Expres) Use SQL Server	at Server Configuration configuration to be used b se 2005 y 2005	n y Aurora Ing	jest Server.			
Speci Speci Speci Speci Speci St	rty Set Editor ify Aurora Inge: y the SQL Server) Use SQL Expres) Use SQL Server IL Server Instanc	at Server Configuration configuration to be used b se 2005 r 2005 e: SOLEXPRESS	y Aurora Ing	jest Server.	5.1.8 Second Sciences		
Speci Speci Speci Speci St	If y Set Editor if y Aurora Inge: y the SQL Server > Use SQL Expres > Use SQL Server QL Server Instanc	at Server Configuration configuration to be used b se 2005 r 2005 e: SQLEXPRESS	y Aurora Ing	jest Server.	2 - 2 - 2 - 2 - 2 - 2 - 2 - 2 - 2 - 2 -		
Specif Specif Specif State State State State State State State State State State State State State State Specif Sp	erty Set Editor ify Aurora Inge: y the SQL Server > Use SQL Expres > Use SQL Server QL Server Instanc er Options unique	at Server Configuration configuration to be used b se 2005 e: SOLEXPRESS to this target	y Aurora Ing	est Server.			
Specif Specif © St St St Us	erty Set Editor ify Aurora Inge: y the SQL Server > Use SQL Expres > Use SQL Server > Use SQL Server QL Server Instanc er Options unique e Options from:	at Server Configuration configuration to be used b se 2005 r 2005 e: SQLEXPRESS to this target	y Aurora Ing	est Server.			

Select the SQL Server configuration that will be used by Aurora Ingest Server. If you choose SQL Server 2005, select the server instance from the dropdown list. If your system has SQL Server already installed (e.g. if the system houses the Aurora Edit database), choose to use the existing SQL Server instance; if not, choose SQL Express.

Software	Deployment options	
	Property Set Editor	×
	Specify Aurora Ingest Server Configuration	
	Specify the Aurora Ingest Server to be used by Aurora Ingest Components. Aurora Ingest Server: x000000000	
	Enter Options unique to this target Use Options from:	< Back Close

Enter the name of the Aurora Ingest Server.

5. If your system has Aurora Ingest RMI devices, also configure deployment options as follows:

Software	Deployment options
GVG_MLib	Enter the name(s) of the K2 Media Server(s) with role of file system server (FSMs)
Aurora	
Suite	Property Set Editor
	DSM Information Enter DSM and shared drive information.
	Specify database server. Database Server.
	Specify shared AV files path. For example, V:WibrintAVFiles
	Shared AV Files: V:WibrintAVFiles
	Please enter the letters, separated by a comma, of the shared AV drives used by this system.
	Shared AV Drives: V
	 Enter Options unique to this target
	O Use Options from:
	< Back Next >

Enter Database server(DSM), Shared AV Files, Shared AV Drives.

Software Deployment options

Cache and Local E Enter the locations f	trive Info or local and cache files		
Select the local AV	iles location. This should be on a high speed local drive.		
Local AV Files:			
D:\VibrintAVFiles			
D:WibrintAVFiles			
D:Wibrink4VFiles	he files location. This should be on a high speed local driv	е.	
D:WibrintAVFiles Select the local cac Cache Files:	he files location. This should be on a high speed local driv	e.	
D:WibrintAVFiles Select the local cac Cache Files: D:WibrintAVCache	he files location. This should be on a high speed local driv	e.	
D:WibrintAVFiles Select the local cao Cache Files: D:WibrintAVCache	he files location. This should be on a high speed local driv	e.	
D:WbintAVFiles Select the local cac Cache Files: D:WibintAVCache	he files location. This should be on a high speed local driv	e.	

Enter Local AV Files, Cache Files.

6. If you have multiple devices of the same type, you can enter deployment options for one of them using the wizard. Then, when you bring up the same wizard on every device, you can choose the **Use options from** radio button and select the first device for which you set options.

SiteConfig copies the options you set for the first device and fills in the blanks on the wizard.

Upgrade software on Aurora Ingest devices

Prerequisites for this task are as follows:

- The devices that you are upgrading are in a deployment group.
- For the software you are upgrading, you have added a newer version of that managed software package to the deployment group.
- You have recently done the SiteConfig "Check Software" operation on the devices you are upgrading.

When you upgrade software, SiteConfig enforces an uninstall of the current version of software before installing the upgrade version. SiteConfig can do the uninstall/install in a single deployment session. If you are upgrading multiple software components, SiteConfig enforces any dependencies by sequencing deployment tasks. SiteConfig provides uninstall deployment tasks and install deployment tasks to indicate the taskflow.

1. In the **Software Deployment | Deployment Groups** tree view, select the device or the group of devices for which you are upgrading software.

The corresponding software deployment tasks are displayed in the Tasks list view.

- 2. For the software you are uninstalling, select the **Deploy** check box in the row for the uninstall task.
- 3. For the software you are installing, select the **Deploy** check box in the row for the install task.

For upgrading all Aurora Ingest devices to this release, deploy the following tasks:

Deploy	Managed Package	Action
✓	AuroraIngest xxxx.xxxx	Uninstall
\checkmark	AuroraIngest 6.5.2.xxxx	Install
✓	IngestServerPrerequisites xxxx.xxxx	Uninstall
✓	IngestServerPrerequisites 6.5.2.xxxx	Install

For Aurora Ingest RMI devices, also deploy the following tasks:

Deploy	Managed Package	Action
✓	AuroraSuite xxxx.xxxx	Uninstall
✓	AuroraSuite 6.5.2.xxxx	Install
✓	GenericISCI x86 xxxx.xxxx	Uninstall
✓	GenericISCI x86 xxxx.xxxx (version must be compatible with K2 SAN)	Install
✓	GVGMLib xxxx.xxxx	Uninstall
✓	GVGMLib xxxx.xxxx (version must be compatible with K2 SAN)	Install

If a message instructs you to upgrade the Discovery Agent, on the control point PC go to the directory to which SiteConfig is installed and in the *Discovery* Agent Setup directory find the *Discovery*Agent_x.x.x.cab file. Add it to the deployment group and deploy the Discovery Agent software as well.

NOTE: If there are dependencies, SiteConfig can enforce that some tasks be deployed together.

4. Click the Start Deployment button.

	Tasks ——					
	Deploy	Device	Managed Package	Action	Status	Details
	~	BH08450166	GrassValleyXxxxxXxxXXxxxXXXXXXXXXXXXXXXXXXXXXXX	Install		
	v	BH08450166	GrassValleyXxxxXXxxXXxxxXXXXXXXXXXXXXXXXXXXXXXX	Uninstall	······	
	V	BH08450166	XXXxxXxx_XxxxxXxxx X.X.X	Install		
	•					Þ
ſ	Show Completed Tasks Options Details					

Deployment tasks run and software is uninstalled. Progress is reported and next steps are indicated in both the Status and Details columns.

- 5. When the Status or Details columns indicate next steps, proceed as follows:
 - When Details displays a **Restart required** link, click the link and when prompted "...are you sure...", click **Yes**.

The device restarts. This restart is required by the Aurora Ingest software uninstall.

Deployment tasks run and software is installed. Progress is reported and next steps are indicated in both the Status and Details columns.

- 6. When the Status or Details columns indicate next steps, proceed as follows:
 - When Details displays a **Restart required** link, click the link and when prompted "...are you sure...", click **Yes**.

The device restarts.

7. Monitor progress as indicated by both the Status and Details column. When finished, the Status column indicates complete.

Upgrade NAS systems

Prerequisites for this task are as follows:

- K2 systems are upgraded to the compatible version of K2 system software.
- Aurora Edit, Ingest, and Playout systems are upgraded to the compatible versions of software.

Upgrade the MediaFrame Proxy NAS (K2 Nearline SAN) to the compatible version of K2 software. Use SiteConfig and deploy software, using steps similar to those for other systems.

- a) Check software on the Nearline SAN's K2 Media Servers.
- b) Add software *. *cab* file to the deployment group that contains the K2 Media Servers.
- c) Upgrade software on K2 Media Servers via a SiteConfig deployment session.

Upgrade Browse and MediaFrame systems

Prerequisites for this task are as follows:

- K2 systems are upgraded to the compatible version of K2 system software.
- Aurora Edit, Ingest, and Playout systems are upgraded to the compatible versions of software.
- K2 Nearline SAN (NAS) systems are upgraded to the compatible version of K2 system software.

Upgrade your Browse and MediaFrame systems to the compatible versions of software. Refer to *Aurora Browse Release Notes* for procedures.

Licensing Grass Valley products

The following sections contain instructions for managing Grass Valley product licenses.

About software licensing

Once the Aurora Ingest software is installed, you are provided with a 30-day temporary license. You need to get a software license number from Grass Valley in order to install the permanent license. Obtaining the software license number is important because you cannot launch channels or configure Aurora Ingest after your 30-day temporary license has expired.

Licenses are requested through the License Wizard and managed through the SabreTooth License Manager, which is installed on the Grass Valley product with the Grass Valley software. The License Wizard and SabreTooth License Manager must be located on the Grass Valley product.

License information is stored in text files that you can manage just like any other file on your system. Licenses are unique to the system for which they are requested and cannot be used on any other machine. You should back up the license text files to a separate drive or as part of a recovery image.

Licenses are based on your system's unique identifier, which is partially derived from your system's Media Access Control (MAC) address. If you change your system's MAC address by performing operations such as changing the System Processor card, you must obtain a new license based on the new MAC address.

Requesting a license

Software licenses are unique to the system for which they are purchased. They cannot be used on any other system. This requires that you provide a generated unique ID for the desired system to Grass Valley, which is then used to create your unique license.

1. Log on to the device that you want to license.

You must log in as a Windows administrator with a local account, not a domain account.

2. Open the License Request Wizard.

Find the License Request Wizard shortcut on the Windows desktop.

The License Request Wizard displays.

3. Read the on-screen instructions, then click Next.

The Customer dialog box displays.

Licensing Grass Valley products

4. Enter the information requested on this page then click Next.

You must provide a valid email address to receive your license file.

The Sales Number dialog box displays.

5. Enter the Sales Order Number in the field then click Next.

Typically the Sales Order Number is found on the Software License sheet that you received with your Grass Valley product.

The Summary dialog box displays.

6. Review the License Request information and click Finish.

A License Request text file, *License_Request_<SalesNumber>.txt*, is generated and saved to the Windows Desktop.

NOTE: If you are requesting licenses for more than one application, be sure to modify the name of the first License Request text file before saving it to your desktop. (In Notepad, use the Save As command.) Otherwise, the second License Request text file will overwrite it.

- 7. Do one of the following:
 - Attach this text file to an email.
 - Paste the text directly into an email message.

You might want to keep a copy of the message for your records.

8. Send the email as instructed by the License Request Wizard.

An email will be sent from Grass Valley to the return email address you specified; your SabreTooth software license will be provided as a text file.

9. Save this email in case you ever need to re-image this machine.

Next add the license to the SabreTooth License Manager.

If you encounter difficulties when requesting a license

If you encounter difficulties running the License wizard, try this alternate method:

- 1. Generate a unique ID of the device where you will install software, as follows:
 - a) Click on the License Manager icon on the Windows Desktop.

The SabreTooth License Manager opens.

- b) Choose File | Generate Unique Id the License Manager.
- c) Click Copy to clipboard to copy the generated ID, and OK to exit.
- 2. Prepare an email that includes the following information:

- Customer Name
- Customer Email
- Sales Order Number
- Unique ID of the device where you will install software.
- 3. Send the email to AuroraLicenses@grassvalley.com.

The SabreTooth license number will be emailed to the email address you specified.

Adding a license

Your software license, *Licenses_<SalesNumber>.txt*, is provided as a text file. Use the License Manager to add this file to your system and enable the desired feature.

1. Click on the License Manager icon on the Windows Desktop. The SabreTooth License Manager opens.

The SabreTooth License Manager opens.

- 2. Do one of the following:
 - Choose File | Import License and navigate to the file location to open the text file.
 - Drag and drop the text file onto the License Manager.

You will now see the permanent license in SabreTooth, as well as any other licenses, permanent or temporary, that have been installed on this machine.

Once you have added the permanent license, you can delete the temporary license. If the temporary license is still in SabreTooth you will continue to get temporary license notifications, even with the permanent license installed, unless you delete the temporary license.

You should save the permanent license to a backup system.

Deleting licenses

Deleting a license disables the feature that it enabled. You might want to delete a temporary license prior to its expiry if you have decided not to purchase the feature. You can delete a temporary license after the permanent license has been installed without disabling the licensed product.

- 1. Select the license in the SabreTooth License Manager.
- 2. Use the Delete key on your keyboard or right click with your mouse and select **Delete**.

Archiving licenses

You can archive your licenses to a secure external location. This allows you to quickly re-install a license should it be deleted or should you have to downgrade and then the licensed software. You can archive multiple licenses at the same time.

NOTE: If you downgrade to an earlier version of the licensed software, make sure to archive the licenses first.

- 1. In the SabreTooth License Manager, select the license or licenses.
- 2. Choose File | Export License to open the Save As dialog box.
- 3. Assign a meaningful name to the file, and save it to the desired location. Grass Valley recommends saving the license file to a USB drive or other external location.

Aurora Ingest licenses

The Grass Valley licenses available at the time of this writing that can be installed on Aurora Ingest are as follows. Contact your Grass Valley representative for more information about licenses.

License	License type
Aurora-Ingest-Number of channels	SabreTooth
Aurora-Ingest-RMI	SabreTooth
Aurora-Ingest-Scheduler	SabreTooth
Aurora-Ingest-VTR Ingest	SabreTooth
Aurora-Ingest-VTR Logging	SabreTooth
Aurora-Ingest-ScheduALL	SabreTooth

Aurora Ingest licenses

Operation considerations

The following sections contain additional information about operating your product systems.

Aurora Ingest Server

- The remote clients should be slaved to the time of day of the Aurora Ingest Server. If an offset is present, scheduled events will be started according to the time of the server component rather than the apparent time of the remote scheduler client.
- Each K2/Summit channel should be connected to either Aurora Ingest or Aurora Playout only. Connecting to both applications at the same time will cause channel conflicts.
- For setting up an Encore router, limiting names of Sources, Destinations, Levels, Salvos, Areas, control panels and other names intended for display on Encore hardware panels to 7 or 8 characters is strongly recommended. Names longer than 8 characters will be truncated and the extra characters will not appear to the panel operator. Names with 8 characters will also have its last character overwritten if a Breakaway condition exists.

Aurora Ingest Scheduler

- Aurora Ingest is designed to run with a screen resolution of 1280x1024 for standard configurations. Some Aurora Ingest windows will not display properly if Windows is configured to use large fonts.
- Prior to installing Aurora Ingest onto a clean system that will support video overlay (Scheduler or VTR Ingest), install the Hauppauge WinTVGo Video Capture Card or Blackmagic Design DeckLink Video Capture Card along with their drivers included on the installation CD.
- The time of day format within the Scheduler is directly related to the current time of day format for the individual client machine. To change this, go to **Start | Control Panel | Regional and Language Options** and launch the Customize tool. Once in the customize tool, enter the Time tab and set your time format accordingly.

NOTE: Changes to the Scheduler's time format will only be seen after a relaunch of the Scheduler application.

- Scheduled records must be separated by at least 10 seconds between the end of the outgoing feed and the start of the incoming feed. To account for this, the default duration of feeds has been set to 59 minutes and 50 seconds in **Tools | Options | General**. It is recommended that any edits to the default duration reflect the 10 second minimum separation.
- The Scheduler will hold onto past events history for three weeks.
- Recurring events can be added for up to three years in advance. These events can be modified later in order to extend the duration of the recurring item.
- For scheduled recurring events, removing a channel from Aurora Ingest Server will reassign those recurring events to other available channels at start time. For non-recurring events, those events will be erased rather than reassigned to other channels.

NOTE: Re-introducing the once removed channel may result in incorrect scheduling for that channel as the database may hold on to events not seen in

the user interface of the scheduler. It is recommended that scheduled events get moved from the channel prior to the channel's removal.

Aurora Ingest Scheduler with ENPS Assignment Grid

- You can refer to the Aurora Ingest System Guide for instructions on configuring ENPS for scheduling events and setting up the ENPS Assignment Grid. If this guide is not yet in your possession, please contact customer support for download information.
- When using ENPS to schedule events, it is important to note that error notifications typically handled within the Aurora Ingest Scheduler will not be as readily available within the ENPS Assignment Grid. For instance, naming conflicts, channel conflicts, elapsed events, etc. will not always be flagged within the ENPS grid. It is important to also monitor the Aurora Ingest Scheduler interface in order to get a more accurate representation of the current activity.

Aurora Ingest RMI

- RMI requires either the Panasonic P2 or Sony XDCAM FAM driver for proper interaction with these types of removable media devices.
- RMI requires the RMI Core 6.5 installation for proper functionality. In addition, RMI should be added into the overall stream count of the shared system as it will be writing directly to the shared storage.
- RMI and Aurora Edit should be installed on separate machines if possible. However, if it's necessary to install them on the same machine, follow the steps below:
 - 1. Uninstall any previous version of Aurora Edit and Aurora Ingest RMI.
 - 2. Run the Aurora Suite installer, choosing to install the Aurora Edit and RMI Core components.
 - 3. Run the Aurora Ingest installer, choosing to install the RMI component.
- RMI should only be installed on Windows XP Operating Systems.
- RMI requires a relaunch after the news DSM is rebooted. The application will not prompt for this, but subsequent import attempts will fail.
- If changing drive volumes for importing clips, the Destination AV Path within **Tools | Options** must be directed to the VibrintAVFiles folder within the desired volume.
- After Sony XDCAM is plugged in and attached to RMI application, XDCAM pop-up will be displayed. To disable XDCAM pop-up in Windows 2000 and Windows XP operating systems, follow the steps below:
 - 1. Go to Start | Run and type in gpedit.msc.
 - 2. Once in, go to Administrative Templates.
 - 3. Then click on System.
 - 4. Once in System, look at the right hand pane and search for Turn off AutoPlay.
 - 5. Open Turn off AutoPlay.
 - 6. Select the Enable option.
 - 7. Select CD-ROM drives in the dropdown and click OK.

Aurora Ingest VTR Ingest

- If multiple clients are pointed to the same VTR, each client will report a successful connection. When operating the VTRs, however, the multiple clients may interfere with each other. It is important to allocate VTRs properly so collisions of this nature do not occur.
- Records have a frame accuracy recording window of +/- 3 frames for the VTR Ingest with K2.
- When controlling a VTR that is in 720p mode, transport commands, such as single frame and ten frame advances may not be frame accurate.

Additional notes

The following sections contain additional information to ensure smooth operation of Aurora Ingest with other systems.

Setting up AMP control on a K2 Client

With Aurora Ingest Server, K2 Media Clients and K2 Summit Production Clients are controlled via AMP Protocol over Ethernet.

To set up AMP control of a K2 Client:

- 1. On AppCenter of the client, click the **Options** button for the desired panel.
- 2. Set the Control setting to either **Remote Only** or **Remote and Local** and the Protocol setting to **AMP**. Repeat this step for each panel that will be controlled remotely by Aurora Ingest.
- 3. In the Ingest Server application, go to **Tools | Options | Media Server** and add the name of the client.
- 4. In the Ingest Server application, go to **Tools | Options | Channel** and add each channel that will be controlled on the K2 or Summit. In the Channel dropdown list, "VTR1" corresponds to the "R1" panel on the K2 or Summit, "VTR2" corresponds to the "R2" panel, etc.

NOTE: Refer to the "Installing and Configuring Aurora Ingest" section of the Aurora Ingest System Guide for more detailed information about configuring media servers and channels.

System Imaging Software

Aurora systems use Acronis imaging software, version 3647, which allows you to back up your system. When the system boots using Acronis Imaging software, select either Safe Version, Full Version, or boot into Windows.

Safe version should normally be used to restore or create the C:\ partition from the backup partition, drive F:\.

Full version loads additional USB drivers, which allows a user to backup or restore with a USB drive. However, the boot process hangs unless the following parameters are entered prior to selecting Full Version:

- 1. Press **F11**.
- 2. Change the boot parameters from *quiet* to *quiet acpi=off noapic*.
- 3. Click **OK**.
- 4. Select the Full Version to load True Image.

NOTE: Acronis imaging software recognizes Rev Pro drives.

Installing software

The software for Aurora Ingest components can be installed on any PC which meets the system requirements for that component.

If you don't have SiteConfig within your operation, you can install or upgrade Aurora Ingest with the procedure below.

To install the Aurora Ingest software on your computer, insert the Aurora Ingest CD-ROM into the machine's CD-ROM drive and follow these instructions:

On this screen	Do this
Welcome	Click Next.
License Agreement	Select I accept and click Next.
Select Features	Specify the Aurora Ingest applications to install: Server , Scheduler , VTR Controller , VTR Ingest , or RMI . With Server component, Microsoft .NET Framework 2.0 and Microsoft SQL Express will also be installed by default. If your system has SQL Server already installed (e.g. if the system houses the Aurora Edit database), choose to use the existing SQL Server instance; if not, choose SQL Express.
Specify Server Configuration	Enter the host name of Aurora Ingest Server that will be used by Aurora Ingest components. Select the SQL Server configuration that will be used by Aurora Ingest Server. If you choose SQL Server 2005, select the server instance from the dropdown list.
Start Installation	Click Next.
Installation Complete	Click Finish.

Installing ScheduALL for Aurora Ingest integration

In order to use VizuAll, Inc.'s ScheduALL with Aurora Ingest, you need to install the ScheduALL application. For a smooth scheduling integration, extra steps need to be adhered to during the installation process. If technical assistance is needed, you can contact ScheduALL product support at 1-954-334-5409 option 1.

These applications are the pre-requisites and must be installed on your machine before proceeding to install ScheduALL.

- Microsoft SQL Server 2005 (For ScheduALL)
- Microsoft SQL Express 2005 (For Ingest)
- Aurora Ingest Server installed and configured
- Visual studio 2005 redistribute SP1 for SchedIngestAPI web service (to be installed automatically by SchedIngestAPI installer)

Additional notes

The following list contains the minimum ScheduALL components required for integration with Aurora Ingest.

- 1. ScheduALL for Windows v4.73.22 (4.74) or greater.
- 2. ScheduALL Authentication Server.
- 3. ScheduALL Ingest API license point.
- 4. Enabled ScheduALL Web Service APIs:
 - WorkOrder Query
 - WorkOrder Delete
 - WorkOrder Modify
 - Work Order Request Create
 - Event Create
 - Event Delete
 - Event Details
 - Event Modify
 - Resource Booking Query
 - Resource Query
 - WorkOrder Details
 - Client Query
- 5. Modules:
 - Scheduling
 - Developer's Toolkit
 - Client/Server
 - WebServiceAPI
 - Ingest Web Service API
- 1. Install Sched4.exe which will install ScheduALL. Select the Network Client option.

The default login username is SUPERVISOR with a blank password.

- 2. Install SchedAuth.exe, which is the Authentication Server for ScheduALL web services.
- 3. Install SchedWebAPI.exe, which is the ScheduALL web service.
- 4. Install SchedIngestAPI (setup.exe), which is the Ingest integration web service.

You can now launch ScheduALL and continue with below steps:

- 1. At the login screen, enter SUPERVISOR and a blank password.
- 2. Deselect the "Use Sample Data" option.
- 3. When prompted to update the database, select "Yes".
- 4. Keep selecting "Yes" and "OK" for permission enquiries.

After completing above steps, ScheduALL should now be operational with Aurora Ingest.

Configuring ScheduALL properties

ScheduALL properties can be configured in the System tab when you select **Tools** | **Options** within Aurora Ingest Server.

Options		×
System Media Server Router Channel	Channel Group Feed VTR Preview	
SDB Server:	localhost	
Backup SDB Server:		
XMOS Server:	localhost	
MediaFrame Server:	kl_mf2	
ScheduAll Server:	10.11.79.179 Configure	
Netcentral Server:		
CompuSat:		
SabreTooth Server:	localhost	
Reference Standard:	NTSC drop frame	
Enable Option to Switch Aspect Ratio:	V	
Default Aspect Ratio:	16:9 💌	
	OK Cancel Apply	

 Click the Configure button, beside the ScheduAll Server setting. The ScheduAll Properties dialog box is displayed.

Additional notes

ScheduAll Properties	
Complete Web Service URL Web Service URL http://10.11.79.179/ScheduALL For example: http://my-schedual	WebServiceAPI/SchedWebServiceAPI.asmx II/scheduallwebserviceapi/SchedWebServiceAPI.asmx
SchedIngestAPI Web Service Config URL Web Service URL http://10.11.79.179/schedingest	tapi/config.aspx Launch
Channels	1
Ingest 9 CH5 CH1 CH2 CH4 CH3	ScheduAll
Router Sources	
Ingest	ScheduAll
Synchronize Events Ready	OK Cancel

2. The Complete Web Service URL and SchedIngestAPI Web Service Config URL are automatically populated once you set the ScheduALL Server within the System tab.

Click the Launch button to launch the SchedIngest API configuration page.

Additional notes

Configure SchedIngestAP	I - Windows Internet Explorer			
🕤 💽 🔻 🙋 http://localho	ost/schedingestapi/config.aspx		💌 😽 🗙 Live Search	
🎓 🍄 🏾 🏉 Configure Sched	IngestAPI		🙆 • 🗟 + 👼 • 🛛	}Page → 🙆 Tools →
Configure S Default Ingest Server Add	tress : IngestServer1	Save		
<u>Channel Assignment :</u> name	Ingest_Server			
Edit Delete Channel 17	IngestServer2			
Edit Delete Channel 23	IngestServer3			
Edit Delete Channel 55	i IngestServer4			
Edit Delete Channel 29	IngestServer3			
Add New Channel :		<mark>a</mark> bababababa Sabababababa		
Channel :				
Server :		Add		
			Local intranet	₹ 100% +

3. Configuration details can be entered as below:

Option	Description
Default Ingest Server Address	Enter the host name or IP address of the default Ingest Server. The default Ingest Server should be the server that is majorly used for scheduling with ScheduALL. By default, all channels on the default Ingest Server can be used with ScheduALL and do not need to be assigned within the Channel Assignment section.
Channel Assignment	Shows channel name and host name of the Ingest Server if you have multiple Ingest Servers connected to your system. You can assign specific channels from multiple Ingest Servers that will be used with ScheduALL. You can also edit or delete channel from this section if needed.
Add New Channel	Add the channel name and host name of the Ingest Server other than the default Ingest Server, if you have multiple Ingest Servers connected to your system. The channel will be displayed in the Channel Assignment section.

4. To edit channel and router resorces of ScheduALL, you need to select the Edit Resources checkbox within the ScheduAll Properties window.

	· · · ·			
Complete Web Service	URL			
Web Service URL hl	tp://10.11.79.179/Schedu4	LLWebServiceAPI/SchedWeb	ServiceAPI.asm	×
Fo	example: http://my-sched	uall/scheduallwebserviceapi/S	chedWebServic	eAPI.asmx
-SchedingestAPI Web 9	ervice Config URL			
Web Service URL	tp://10.11.79.179/scheding	estapi/config.aspx		Launch
🔽 Edit Resources 🚽				
Channels				
Ingest		ScheduAll		
Channel 8 Channel 7		Channel 8 Channel 7		
Channel 6		Channel 6		
Channel 5		Channel 5		
Channel 4 Channel 3		Channel 4 Channel 3		
Channel 2		Channel 2		
Channel 1		Channel I		
Router Sources				
Ingest		ScheduAll		
SRC1		SRC1		
SRC2 SRC3		SRC3		
SRC4		SRC4		
SRC5		SHC5 SBC6		
SRC7		SRC7		
1				
Synchronize Events	1		ОК	Cancel
-,				

You have to wait for the query to ScheduALL to complete, as this may take a few minutes. Once it's done, the dialog status bar will show 'Ready'.

- 5. All channels and router sources that had been set up on your Ingest Server will be displayed. You need to map your existing channels and router sources on Ingest Server to existing channels and router sources on ScheduALL.
- 6. Select your particular channel or router source for Ingest Server, double-click on the ScheduALL resource item and select an item that you want to map with in the dropdown list.

Channel names and router sources should match respectively for both applications. If you have multiple Aurora Ingest Servers within your operation, each channnel on those Ingest Servers must be configured with unique names to avoid scheduling conflicts with ScheduALL.

7. Click **OK** after you have finished configuring ScheduALL properties.

Configuring ScheduALL application

ScheduALL application needs to be set up to include Aurora Ingest Room and the URL of SchedIngestAPI Web Service for the scheduling integration to be successful.

- 1. Launch the ScheduALL application.
- 2. Select File | Supervisor Options | System Preferences | General .
- 3. Click on the System Options tab and scroll down to the Request Room Options.

Main Overtime Multi-Region Settings General System Options		_
escription	Value	🖌 Ok
Keep Default Values set in DTK when copying Work Orders	Yes	
Allow Concurrent User Sessions under the .NET Framework	Yes	X Cancel
Assign Copy Id upon Work Order Copy	No	
Create Visual Path Image in Reports	No	🗎 🗎 Print
Maximum Visual Path Image Width(In Pixels) :	800	
Disregard Library Episode Ownership	No	
Login Method for Switch User Feature:	User Name/Password	
Enable Alternate Vendor Invoice Reconcile Method	No	
Assign Cost Unit of Measure per Default set in Vendor Cost Maintenance	No	
Allow Duplicate Vendor Invoices with Unique Invoice Dates	No	
Prompt to Print Label when Committing/Saving New Library Entry	No	
Request Room:	Aurora Ingest	
Request Room 2:		
Quote Attachment File:		
Mandatory Resource Questions Must be Answered by Status:	Confirmed	
Append new Work Order/Trouble Ticket Notes to:	<bottom list="" of=""></bottom>	
Default Status for Trouble Ticket:	Request	
Default Trouble Ticket Client:		
Set to Hold for Review at statuses:	0 status(es)	
Enforce Booking of Volume Resources to Count > 0	No	

- 4. Select the Aurora Ingest Room.
- 5. Then, scroll down to Ingest options.

Additional notes

Aain Overtime Multi-Region Settings General System Options		-
escription	Value	V Ok
- Other Default Event Status	None	
 Day in Lieu Default Event Status 	None	X Cancel
 Available Block Default Event Status 	None	
 Sabbatical Default Event Status 	None	🖻 Print
 Other Paid Activity 1 Default Event Status 	None	
 Other Paid Activity 2 Default Event Status 	None	
 Other Paid Activity 3 Default Event Status 	None	
 Other Non Paid Activity 1 Default Event Status 	None	
 Other Non Paid Activity 2 Default Event Status 	None	
 Other Non Paid Activity 3 Default Event Status 	None	
Company Holiday Default Event Status	None	
e SMS		
📙 🧁 Gateway Login		
- Gateway Password		
Max Message Length (0=unlimited)	0	
E Ingest		
	http://localhost/ScheduALLIn	
— Login Required	No	
— UserName	supervisor	
Password		

6. Enter the URL of the SchedIngestAPI Web Service.

The default URL is *http://localhost/SchedIngestAPI/SchedIngestAPI.asmx*. If the web service had been installed on another machine, edit the URL to include the hostname or IP address of that machine.

7. Click **OK** to save the setting.

Known Issues

The following limitations are present in this release of software. If you wish to obtain more information about these limitations, please mention the reference numbers.

Aurora Ingest - Server

CR80235	Description:	The extra "_b" appended to backup feed clip name could break conformance from remote system.
	Workaround:	Change the following value in the Windows registry from 1 to 0: HKEY_LOCAL_MACHINE\SOFTWARE\Grass Valley\Aurora Ingest\Server\Feed\Use Backup Clip Name
CR86146	Description:	With more than 100 hours of storage space remaining on K2, Ingest misreports storage.
	Workaround:	Aurora Ingest will begin to properly report storage once the capacity has fallen below 100 hours.

Aurora Ingest - Scheduler

CR78916	Description:	Crash record of gang-roll events could fail if the default clip name consists of more than 32 characters.
	Workaround:	As the current limit to a default clip name is 26 characters, ensure that router source name (which gets added to default clip name for gang roll events) consists of less than 6 characters. Hence, the default clip name would not consist of more than 32 characters.
CR87061	Description:	Having completed recurring events in Scheduler prevents the ability to create a series with the same name going forward.
	Workaround:	Delete the event from today that already finished recording. Now Scheduler will let you add a new series with that name.
CR89491	Description:	When custom metadata fields are reordered in Aurora Browse, they do not get reordered in Ingest.
	Workaround:	Close and relaunch Schedule client in order to see the updated order of custom fields.
CR94269	Description:	Thumbnails don't appear for keywords marked using X-keys.
	Workaround:	Marking keywords manually through the MediaFrame plug-in window will create a keyword if proxy media exists.
CR94791	Description:	If crash record default bin doesn't exist on media server, Scheduler shows "Error obtaining clip duration from the media server".
	Workaround:	It is highly recommended that record directories exist on the media client prior to attempting records or sends.

Known Issues

CR99287	Description:	On clean install with no MediaFrame configuration, Scheduler default UI has big blank Search window.
	Workaround:	This window is harmless. Close the dialog and subsequent relaunches of the Scheduler will not present the window.
CR99410	Description:	X-keys generic Keyword button adds keyword with blank name, rather than default name.
	Workaround:	When adding a keyword button for X-Keys, opt to add a name for the keyword.
CR104168	Description:	ScheduALL status light is red while functionality is OK.
	Workaround:	None.
CR105606	Description:	For events added through Scheduler, ScheduALL doesn't send update to Scheduler after modifying channel, router, or location.
	Workaround:	After modifying the channel, router or location on ScheduALL, users need to manually change the channel, router or location of the same event on Scheduler.

Aurora Ingest - RMI

CR98692	Description:	If logged in as user without "Modify" rights to V:\VibrintXDCAMFiles, canceling RMI cache prevents it from caching again.
	Workaround:	You need to turn on Modify access for the V:\VibrintXDCAMFiles folder if using RMI as a non-administrator in an environment where Security is enabled.
CR98929	Description:	Clips that were part of a merged import don't show "Exists" status after relaunching RMI.
	Workaround:	No workaround at this time.